

# **Smart Video Evaluation Toolkit – Sample Application User Guide for Windows**

---

*Sep 2020*



You may not use or facilitate the use of this document in connection with any infringement or other legal analysis concerning Intel products described herein. You agree to grant Intel a non-exclusive, royalty-free license to any patent claim thereafter drafted which includes subject matter disclosed herein

No license (express or implied, by estoppel or otherwise) to any intellectual property rights is granted by this document.

All information provided here is subject to change without notice. Contact your Intel representative to obtain the latest Intel product specifications and roadmaps.

The products described may contain design defects or errors known as errata which may cause the product to deviate from published specifications. Current characterized errata are available on request.


Copies of documents which have an order number and are referenced in this document may be obtained by calling 1-800-548-4725 or by visiting: <http://www.intel.com/design/literature.htm>

Intel technologies' features and benefits depend on system configuration and may require enabled hardware, software or service activation. Learn more at <http://www.intel.com/> or from the OEM or retailer.

Intel MediaSDK, OpenVINO and the Intel logo are trademarks of Intel Corporation in the U.S. and/or other countries.

\*Other names and brands may be claimed as the property of others.


Copyright © 2020, Intel Corporation. All rights reserved.



## Contents

---

<b>1.0</b>	<b>Installation Guide.....</b>	<b>5</b>
1.1	System installation.....	5
1.2	Install OpenVINO 2020.2 and Media SDK.....	5
1.3	Build SVET sample application and dependent libraries .....	7
1.4	Prepare inference model .....	11
1.5	Prepare the video clips for testing.....	12
<b>2.0</b>	<b>Run SVET sample application .....</b>	<b>13</b>
2.1	Check environment variables.....	13
2.2	Modify the video path in parameter file .....	14
2.3	Run video_e2e_sample application .....	14
2.3.1	16-channel video decoding, face detection, composition, encode and display .....	15
2.3.2	4-channel video decoding, human pose estimation, composition, and display .....	16
2.3.3	4-channel video decoding, vehicle and vehicle attributes detection, composition, encode and display .....	17
2.3.4	16-channel RTSP video decoding, face detection, composition, encode and display .....	18
2.3.5	16-channel RTSP video decoding, RTSP stream storing, face detection, composition, encode, and display .....	18
2.3.6	HDDL inference, face detection and GPU composition, encode, display .....	18
2.4	Usage of media codec, inference and display parameters in par file .....	19
2.4.1	New parameters in Par file.....	19
2.4.2	Decode, encode and display parameters.....	20



## Revision History

---

Date	Revision	Description
2020/05/26	0.5	Initial release
2020/09/07	0.6	Fixed some bug

***Note: Releases in the table are listed in reverse order so that the latest/newest is in the top row.***



## 1.0 Installation Guide

---


### 1.1 System installation

Install Windows 10 enterprise on any Intel® Core™ or Atom™ processors. (Better to be after the 5th generation Core™ and Baytrail for Atom™ processors)

Set up the network correctly

### 1.2 Install OpenVINO 2020.2 and Media SDK


The sample application video\_e2e\_sample depends on OpenVINO libraries, Media SDK library and FFmpeg library. We suggest users to install OpenVINO 2020.2 package from <https://software.intel.com/en-us/openvino-toolkit>.



Please Install OpenVINO 2020.2 according to [https://docs.openvino toolkit.org/latest/\\_docs\\_install\\_guides\\_installing\\_openvino\\_windows.html](https://docs.openvino toolkit.org/latest/_docs_install_guides_installing_openvino_windows.html)

By default, OpenVINO 2020.2 is installed to "C:\Program Files (x86)\IntelSWTools\openvino\_2020.2.117".

Make sure the Graphic driver is installed correctly in the Windows device manager, it should look like below status.



If the driver is not installed properly, you can download the Graphic driver by below link:

[https://downloadcenter.intel.com/product/80939/Graphics-Drivers?elq\\_cid=3226637&erpm\\_id=5670311](https://downloadcenter.intel.com/product/80939/Graphics-Drivers?elq_cid=3226637&erpm_id=5670311)

Please Install Media SDK 2019 R1 according to:

<https://software.intel.com/en-us/media-sdk/choose-download/client>


Media SDK installation guide as below:

- 1, Install the SDK and library files. (Note Installation requires full administrative rights.)
- 2, Set up the Microsoft Visual Studio\* environment with the SDK and library directories.
- 3, Run the Intel\_Media\_SDK\_20xx\_xx.msi installer. The default installation directory is c:\Program Files (x86)\IntelSWTools\Intel(r)\_Media\_SDK\_XXXX where XXXX is the year and version number.
- 4, After installation, restart your system to initialize INTELMEIASDK\_WINSOCK\_PATH and install the remaining files.

Other Media SDK Installation document, you can reference to:

<https://software.intel.com/en-us/media-sdk/documentation/featured-documentation>

when you build video\_e2e\_sample, it will depend on Media SDK sample code (sample\_common and sample\_plugins), which you can find in below folder, after Media SDK installed:



C:\Users\Myname\Documents\Intel® Media SDK 2019 R1 - Media Samples 8.4.27.25\

And for the RTSP function, this video\_e2e\_sample building also depends on FFmpeg library, it can be downloaded from:

<https://ffmpeg.zeranoe.com/builds/win64/>

in dev and shared folder, download ffmpeg-20191224-287620f-win64-dev.zip and ffmpeg-20191224-287620f-win64-shared.zip, and extracted to

C:\Program Files (x86)\ffmpeg\ffmpeg-20191224-287620f-win64-dev\

C:\Program Files (x86)\ffmpeg\ffmpeg-20191224-287620f-win64-shared\

which will be used to compile the video\_e2e\_sample in visual studio.

## 1.3 Build SVET sample application and dependent libraries

Download svet\_e2e\_sample\_w.zip sample package, or you can git clone the svet\_e2e\_sample\_w code from github <https://github.com/intel-iot-devkit/concurrent-video-analytic-pipeline-optimization-sample-w>

and extract it to a folder, such as

C:\Users\Myname\Downloads\svet\_e2e\_sample\_w\svet\_e2e\_sample\_w


Copy the Media SDK dependent sample code to svet\_e2e\_sample\_w,

```
cp C:\Users\Myname\Documents\Intel® Media SDK 2019 R1 - Media Samples
8.4.27.25\sample_common
C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w

cp C:\Users\Myname\Documents\Intel® Media SDK 2019 R1 - Media Samples
8.4.27.25\sample_plugins
C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w
```

Then the folder will look like below.

Clipboard	Organize	New	Open	Select
This PC > Downloads > svet_e2e_sample_w > svet_e2e_sample_w				
<input type="checkbox"/>	Name	Date modified	Type	Size
✓	.git	2020/4/8 10:40	File folder	
↑	par_file	2020/4/8 10:40	File folder	
	sample_common	2020/4/8 10:46	File folder	
	sample_plugins	2020/4/8 10:46	File folder	
	video_e2e_sample	2020/4/8 10:49	File folder	
	test.txt	2020/4/7 10:19	Text Document	1 KB




Open Visual studio (suggest to use Visual studio 2017 and Windows SDK 10), Windows SDK download link:

<https://go.microsoft.com/fwlink/p/?LinkId=838916>


Open File->Open Project, choose:

C:\Users\Myname\Downloads\svet\_e2e\_sample\_w\svet\_e2e\_sample\_w\video\_e2e\_sample\sample\_multi\_transcode.vcxproj


If the project load successes, it will look like below.




Choose “Release” and “X64”, and Right Click “Sample\_multi\_transcode”, choose Build, it will start building.




You may meet some issue like below, “cannot find source file “libavformat/avformat.h”









You should check the Additional Include Directories, by right clicking. "sample\_multi\_transcode" and choose "properties", select C/C++->General->Additional Include Directories.




Additional Include Directories looks like below:




Click the down arrow at the end and Click the <Edit...> button, you will see blow dialog, please make sure, below Include folder can be found on your PC.



And the same thing for the “Additional Library Directories” and “Additional Dependencies” in Linker->General->Additional Library Directories and Linker->Input->Additional Dependencies.



Additional Dependencies, click the down arrow and <Edit...>, then a dialog jump out, it looks like below:



## 1.4 Prepare inference model

Download inference IR file through script\download\_IR\_file.py

You can execute below script in windows console (requires full administrative rights):

```
Cd svet_e2e_sample_w\script
python _IR_file.py
```

you will find all the inference IR file in folder  
svet\_e2e\_sample\_w\video\_e2e\_sample\model\:

below IR file is needed for later test.

This PC > Downloads > svet_e2e_sample_w > svet_e2e_sample_w > video_e2e_sample > model				
	Name	Date modified	Type	Size
access	face-detection-retail-0004.bin	2019/11/11 15:09	BIN File	1,149 KB
ktop	face-detection-retail-0004.xml	2019/11/11 15:09	XML Document	47 KB
vnloads	human-pose-estimation-0001.bin	2019/11/11 15:11	BIN File	8,006 KB
uments	human-pose-estimation-0001.xml	2019/11/11 15:11	XML Document	65 KB
ures	vehicle-attributes-recognition-barrier-0039.bin	2019/11/7 11:05	BIN File	1,223 KB
cplicity	vehicle-attributes-recognition-barrier-0039.xml	2019/11/7 11:05	XML Document	18 KB
iple_multi_trans	vehicle-license-plate-detection-barrier-0106.bin	2019/11/7 11:05	BIN File	1,257 KB
T	vehicle-license-plate-detection-barrier-0106.xml	2019/11/7 11:05	XML Document	98 KB




## 1.5 Prepare the video clips for testing

If you don't have video clip for testing, you can download sample videos for face detection from <https://raw.githubusercontent.com/intel-iot-devkit/sample-videos/master/head-pose-face-detection-male.mp4>, human pose estimation from <https://github.com/intel-iot-devkit/sample-videos/blob/master/classroom.mp4> and vehicle detection sample video from <https://github.com/intel-iot-devkit/sample-videos/blob/master/car-detection.mp4>. Since SVET sample application only supports element stream, you can use bellow command to extract the element stream from MP4 file:

```
ffmpeg -i classroom.mp4 -c:v libx264 -an -bsf:v h264_mp4toannexb -r 30 -g 60 -b:v 4000k -bf 0 classroom.h264
```

After that, classroom.h264 can be used as input video stream.

If you want to do performance test, we suggest you to format the video clips bitrate as 4Mbps. if it's 1080P video stream, GOP size as 60, reference frame as 1, no B frames, FPS as 30. Then you can get a test result near our test result.




## 2.0 Run SVET sample application

### 2.1 Check environment variables


Setting below debugging environment path to Debugging->Environment.

```
PATH= C:\Program Files (x86)\ffmpeg\ffmpeg-20191224-287620f-win64-shared\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\external\hddl\bin;C:\Program Files (x86)\IntelSWTools\openvino\opencv\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\external\tbb\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\nggraph\lib;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\bin\intel64\Release;%PATH%
```



If you are running the application in console, you should set the environment path by:

```
set C:\Program Files (x86)\ffmpeg\ffmpeg-20191224-287620f-win64-shared\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\external\hddl\bin;C:\Program Files (x86)\IntelSWTools\openvino\opencv\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\external\tbb\bin;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\nggraph\lib;C:\Program Files (x86)\IntelSWTools\openvino\deployment_tools\inference_engine\bin\intel64\Release;%PATH%
```




## 2.2 Modify the video path in parameter file

Modify the video path (following “-i::h264”) of **every line** in example par file under C:\Users\Myname\Downloads\svet\_e2e\_sample\_w\svet\_e2e\_sample\_w\par\_file\n4\_1080p\_hp.par.

```
-i::h264 content\2.h264 -dc::rgb4 -join -hw_d3d11 -threads 3 -async 10 -timeout 3600 -o::sink -vpp_comp_dst_x 0 -v
-i::h264 content\2.h264 -dc::rgb4 -join -hw_d3d11 -threads 3 -async 10 -timeout 3600 -o::sink -vpp_comp_dst_x 960
-i::h264 content\2.h264 -dc::rgb4 -join -hw_d3d11 -threads 3 -async 10 -timeout 3600 -o::sink -vpp_comp_dst_x 0 -v
-i::h264 content\2.h264 -dc::rgb4 -join -hw_d3d11 -threads 3 -async 10 -timeout 3600 -o::sink -vpp_comp_dst_x 960
-vpp_comp_only 4 -w 1920 -h 1080 -async 10 -join -hw_d3d11 -i::source -ext_allocator
```

Set the par file as Command Arguments:

-par ..\par\_file\n16\_1080p\_fd.par




If run the application in console, you should run below command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n4_1080p_fd.par
```

## 2.3 Run video\_e2e\_sample application

Choose the Debug->Start Debugging, Then the application can run.




When running 16-channel inference, loading of inference models can take long time. due to the run time building of OpenCL kernel for each model. It's recommended to enable OpenCL kernel cache by make a "cl\_cache" folder in C:\Users\Myname\Downloads\svet\_e2e\_sample\_w\svet\_e2e\_sample\_w\video\_e2e\_sample\ Then only one time OpenCL kernel building is required, after that, the built kernel can be loaded from cl\_cache directory.

### 2.3.1 16-channel video decoding, face detection, composition, encode and display

Command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n4_1080p_fd.par
```

The face detection inference is specified by "-infer::fd ./model" in the par file. " ./model " is the directory that stores human pose detection model IR files.



If you want to stop the application, close the console.

If you want to play 200 frames in each decoding session, you can append “-n 200” to parameters lines starting with “-i” in par files.

### 2.3.2 4-channel video decoding, human pose estimation, composition, and display

Command:


```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample  
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n4_1080p_hp.par
```

Replace the “-par ..\par\_file\n16\_1080p\_fd.par” to “-par ..\par\_file\n4\_1080p\_hp.par”

The human pose detection inference is specified by “-infer::hp ./model” in the par file.  
“./model” is the directory that stores human pose estimation model IR files.

Below picture is the screenshot of this demo.





### 2.3.3 4-channel video decoding, vehicle and vehicle attributes detection, composition, encode and display


Command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n4_1080p_vd.par
```

Replace the “-par ..\par\_file\n16\_1080p\_fd.par” to “-par ..\par\_file\n4\_1080p\_vd.par”

The vehicle and vehicle attributes detection inference is specified by “-infer::vd ./model” in the par file. “./model” is the directory that stores vehicle and vehicle attributes detection model IR files.

Below picture is the screenshot of this demo.





### 2.3.4 16-channel RTSP video decoding, face detection, composition, encode and display

Command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample  
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n4_1080p_rtsp.par
```

Replace the “-par ..\par\_file\n16\_1080p\_fd.par” to “-par ..\par\_file\n4\_1080p\_rtsp.par”

To use RTSP video stream instead of local video file, you can modify the par file and use RTSP URL to replace local video file path.

```
-i:h264 rtsp://192.168.0.8:1554/simu0000 -join -hw -async 4 -dec_postproc -o::sink -vpp_comp_dst_x  
0 -vpp_comp_dst_y 0 -vpp_comp_dst_w 480 -vpp_comp_dst_h 270 -ext_allocator -infer::fd ./model
```

### 2.3.5 16-channel RTSP video decoding, RTSP stream storing, face detection, composition, encode, and display

Command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\video_e2e_sample  
..\_build\x64\Release\video_e2e_sample.exe -par ..\par_file\n16_1080p_rtsp.par
```


Replace the “-par ..\par\_file\n16\_1080p\_fd.par” to “-par ..\par\_file\n16\_1080p\_rtsp.par”

The name of RTSP streaming local file is specified by option “-rtsp\_save filename” in decoding session in par file. User can choose one or more sessions to invoke the RTSP stream storing

### 2.3.6 HDDL inference, face detection and GPU composition, encode, display

To perform inference on Intel® Vision Accelerator Design with Intel® Movidius™ VPUs, the following additional installation steps are required:

1. If your Intel® Vision Accelerator Design with Intel® Movidius™ VPUs card requires SMBUS connection to PCIe slot (Raw video data card with HW version Fab-B and before), install the SMBUS driver:
  - a. Go to the <INSTALL\_DIR>\deployment\_tools\inference-engine\external\hddl\SMBusDriver directory, where <INSTALL\_DIR> is the directory in which the Intel Distribution of OpenVINO toolkit is installed.
  - b. Right click on the hddlsmbus.inf file and choose **Install** from the pop up menu.



Command:

```
cd C:\Users\Myname\Downloads\svet_e2e_sample_w\svet_e2e_sample_w\script
Run_FD_HDDL_test.bat
```

If you want to enable HDDL human pose detection or vehicle detection, you need to change the par\_file\n4\_1080p\_fd\_HDDL.par

Replace the "-infer::fd" to "-infer::hp" or "-infer::vd".

## 2.4 Usage of media codec, inference and display parameters in par file

### 2.4.1 New parameters in Par file

Comparing to original sample\_multi\_transcode, we add some new parameters.

Parameter	Usage
-infer::infer_type ir_file_dir	Specify the inference type and directory that stores the IR files.  Examples:  -infer::fd ./model →face detection  -infer::hp ./model →human pose estimation  -infer::vd ./model →vehicle and vehicle attributes detection
-infer::Device_type	-infer::GPU →Running inference workload on GPU  -infer::HDDL →Running inference workload on HDDL card
-i::h264 rtsp://url	Specify the source H264 file with RTSP URL
-rtsp_save filename.h264	Save RTSP stream to local file. This parameter must be used together with "-i::h264 rtsp://url".  If the whole line of session parameters only contains "-i::h264 rtsp://url -rtsp_save filename.h264" and don't have other decoding parameters, we call such sessions as RTSP stream storing session and they must be put into a separated par file.
-infer::interval	Set the inference frame interval, -infer::interval 3, means every 3 frame, do one time inference operation.
-infer::max_detect	Set max detect target number, -infer::max_detect 1, means detect 1 target in a frame.



-o::raw /dev/null	Drop decode result, do not do encode and display.
-------------------	---

## 2.4.2 Decode, encode and display parameters

Below table explains the parameters used in example par files. The full parameter list can also be found at [https://github.com/Intel-Media-SDK/MediaSDK/blob/master/doc/samples/readme-multi-transcode\\_linux.md](https://github.com/Intel-Media-SDK/MediaSDK/blob/master/doc/samples/readme-multi-transcode_linux.md)

Parameter	Usage
-i:h264   h264 input_video_filename	Set input file and decoder type
-o:h264   h265 output_video_filename	Set output file and decoder type
-o::sink	The output will be passed to the sink sessions,, e.g. encoding session or composition session
-i::source	The input is coming from source sessions like decoding session
-vpp_comp_dst_x 0 -vpp_comp_dst_y 270 -vpp_comp_dst_w 480 -vpp_comp_dst_h 270	(x, y) position and size of this stream in composed stream
-join	Join session with other session(s). If there are several transcoding sessions, any number of sessions can be joined. Each session includes decoding, preprocessing (optional), and encoding
-hw_d3d11	GPU will be used for HW accelerated video decoding, encoding and post-processing.
-async <async_depth>	Depth of asynchronous pipeline.
-threads <thread_number>	Number of session internal threads to create
-ext_allocator	Force usage of external allocators
-n	Number of frames to transcode  (session ends after this number of frames is reached). In decoding sessions (-o::sink) this parameter limits number of frames acquired from decoder. In encoding sessions (-o::source) and transcoding sessions this parameter limits number of frames sent to encoder.
-fps <fps>	Transcoding frame rate limit
-vpp_comp <sourcesNum>	Enables composition from several decoding sessions. Result is written to the file
-vpp_comp_only <sourcesNum>	Enables composition from several decoding sessions. Result is shown on screen.



<code>-ec::nv12   rgb4</code>	Forces encoder input to use provided chroma mode.
-------------------------------	---